PODEŠAVANJE ŠTAMPANJA – COBISS Lib

Za upotrebu perifernih uređaja, kao što su štampači, RFID ploče, fioka kase itd, biblioteka mora da instalira servis COBISS DGW. Ovaj servis omogućava komunikaciju između aplikacije COBISS Lib i perifernih uređaja. Postupak instalacije servisa COBISS DGW i uređivanje podešavanja opisani su u uputstvima <u>Instalacija i podešavanje servisa COBISS DGW</u>. DGW radi samo u Windows 10 i 11 (x64-bit).

Za štampanje iz COBISS Lib-a potrebno je postaviti podrazumevane vrednosti štampanja u Kontrolnoj tabli.

Postoje dva načina za podešavanje drajvera (slika 1 i 2), i na **oba mesta treba proveriti da li je drajver podešen** u skladu sa <u>uputstvom</u> za određeni model štampača.

🖶 ZDesigner GK420t Prop	perties				×
Nastavitve tiskalnika Pred	dloge Jezik	Pisave čr	tnih kod	Ukazne pisa	ave Vizitka
General Sharing	Ports	Advanced	Color M	anagement	Security
ZDesign Location: Comment:	er GK420t				
Model: ZDesigne Features Color: No	er GK420t	Paper a	vailable:		
Double-sided: No		User d	efined		~
Staple: Unknown					
Speed: Unknown					
Maximum resolution:	: 203 dpi				\vee
1.	Pro	eferences		Print Test	Page
	ОК	Cancel		Apply	Help

Nastavitve tisk	alnika	Predloge	Jezik	Pisave č	rtnih kod	Ukazne pisav	e Vizitka
General	Sharing	Ports	Ad	vanced	Color N	lanagement	Security
Always a	vailable	:					
○ Available	e from	00:00)	*	То	00:00	*
0				Jammand			
Priority:	1	▲ ▼					
Driver	7Dec	·				New D	
Spool pr Start Start	int docu printing printing	uments so g after last g immediat	program page is s tely	n finishes spooled	printing f	aster	iver
Spool pr Start O Start O Print dire	printing printing actly to	uments so g after last g immediat	program page is s tely	n finishes spooled	printing f	aster	IVer
Spool pr Start Orint dire Hold mis	printing printing actly to p	uments so j g after last g immediat the printer ed docume	program page is s tely ents	n finishes spooled	printing f	aster	
 Spool pr Start Start Print dire Hold mis Print spo 	printing printing ectly to resonance	uments so j g after last g immediat the printer ed docume ocuments f	program page is : tely ents irst	n finishes spooled	printing f	aster	
 Spool pr Start Start Print dire Hold mis Print spo Keep print Keep print 	printing printing actly to smatche poled do nted do	uments so g after last g immediat the printer ed docume ocuments f cuments	program page is s tely ents irst	n finishes spooled	printing f	aster	
 Spool pr Start Start Print dire Hold mis Print spo Keep print Enable a 	printing printing ectly to smatche poled do nted do dvanced	uments so g after last g immediat the printer ed docume ocuments f cuments d printing f	program page is s tely ents irst	n finishes pooled	printing f	aster	IVer

Ako biblioteka koristi mrežne štampače ili server za štampanje, za prijavu u Cobiss3JettyService mora se koristiti korisničko ime i lozinka za domen (<u>Instalacija i podešavanje servisa COBISS</u> <u>DGW</u> – Poglavlje 3).

Ako biblioteka nema svoj domen onda se upotrebljava lokalni račun, a umesto domena upisuje se ime računara u obliku: **ime računara****korisnik**.

Lozinka za unos je ista kao i za prijavu na korisnički nalog. Ukoliko lozinka nije podešena, treba promeniti postavke u Local Security Policy:



U CMD se može izvršiti komanda >> echo %USERDOMAIN% << čime se dobija ime domena ili ime računara.